Print Options



What is the 'Print Area'?

When using the print dialogue box it is possible to specify whether to print the entire workbook, selection or the active sheet. You can also select an section of your sheet and set this as the 'Print Area' meaning this will be only this area that will print.

How do I set the Print Area?

- 1. Select the cells you wish to print.
- 2. Click to display the 'Page ne Layout' ribbon.
- 3. Click the 'Print Area' drop down menu button.
- Insert Page Layout Formulas Data Review Margins Orientation Size X X X X
- 4. Click 'Set Print Area'.

Follow steps 1-3 again, choosing 'Clear Print Area' to remove this selection.

How do I print my worksheet over a set number of pages?

You can use the 'Scale to Fit' options to alter the number of pages over which your sheet should print.

- 1. Click to display the 'Page Layout' ribbon.
- 2. In the 'Scale to Fit' section use the spin controls to adjust the print scale.

OR

Use the 'Width' and 'Height' drop down menus to instruct

Excel to print over a specific number of pages.

view	View	Help	Q	Tell m	e wha	at you want t
	田	Width	Aut	utomatic		Gridlines
9		1 Height:	Aut	omatic		ew
ound	Print Titles	Scale:	1 p	age		int
	Trues 1	Scale	2 pi	ages	N	et Op
	181	Scale	3 pi	ages	3	et Op
			4 pi	ages		
			E			

In the example opposite the text will shrink to fit your full spreadsheet onto 2 pages wi

breaks are ignored when the 'Fit to' option is used.

es wio	de and	d 3 pag	es tall.	Ma	nual pa	age
round	Print Titles	Width:	and the second second) • •	Gridlines View Print	Headin Vin Pr
	5	Scale	to Fit	15	Sheet O	ptions

What other print options are available?

It is possible to select various other options before printing. eg to print/not print gridlines etc.

- 1. Click to display the 'Page Layout' ribbon.
- 2. Click to show the 'Page Setup' dialogue box. The 'Page Setup' dialogue
- box will be displayed as shown below. 3. Click the 'Sheet' tab.

ntation	Size *	Area *	Teaks	Background	Print Titles	🖳 Sca
	Pag	ge Setup			(G) :

- 4. In the 'Print' section tick the options required.
 - Gridlines: All gridlines are printed (see also 'How do I print the gridlines?').
 - Black and White: Print the worksheet in black and white even if using a colour printer (saves ink and money).

Page Set	up				?	>
Page	Margins	Header/Footer	Sheet			
Print ar	ea:					1
Print tit						
Rows	to repeat at	top:				1
10.00	to repeat at ins to repeat	- Sec				1
Colum Print	22/1	at left:	mments:	(None)		70.00

- Draft Quality: Prints
 at slightly less than normal quality.
- Row and column headings: The column headers (A-...) and row headers (1-...) will print (see also 'How do I print the row/column headers?').
- **Comments:** Any comments added to cells will be printed.
- **Cell errors as:** Select how errors are displayed when printed. The illustrations below show the error in the worksheet (cell B3) and how the worksheet will print when the 'cell error as' value is to to 'blank'.

How do I print the gridlines?

- 1. Click the 'Page Layout' ribbon.
- 2. Tick the 'Print' box in the 'Gridlines' section.

How do I print column/row headers?



- 1. Click the 'Page Layout' ribbon.
- 2. Tick the 'Print' box in the 'Headlines' section.





Available during office hours. For critical support at other times refer to the out-of-hours phone list.

Part of the 'How do I...' series of helpsheets. For more, visit ictsupport.key.org.uk